

SmartSnap Command

Retain multiple
snapshots

SMARTSNAP.EXE virtualdisk [UUID] /
KEEP:n

Compaq SANworks™

Virtual Replicator Version 2.0

Commands

The SnapMgr and NDMgr commands at a glance

© 2000 Compaq Computer Corporation.

Compaq and StorageWorks Registered in United States Patent and Trademark Office and other jurisdictions.

SANworks is a trademark of Compaq Information Technologies Group, L.P.

Microsoft, Windows, and Windows NT are registered trademarks of Microsoft Corporation.

AV-RENNC-TE

Use these commands at:

- **Microsoft Windows NT command prompt:**
C:\> SNAPMGR SNAPSHOT "My Snapshot" /DELETE
- **SnapMgr or NDMgr prompt:**
C:\> SNAPMGR
SnapMgr> SNAPSHOT "My Snapshot" /DELETE

SnapMgr Commands

Show available drive letters	DRIVES [/NODE:nodename]
Manage remote computer	MANAGE computername
Manage local computer	MANAGE /LOCAL
Show managed computer	MANAGE

Create a pool	POOL pool /UNITS:disknumbers
Add a storage unit	POOL pool /ADD:disknumber
Delete a pool	POOL pool /DELETE
Show pools	POOL [pool] POOL pool [/STATISTICS /UNITS]

Create a snapshot	SNAPSHOT snapshot /PARENT:parent
Map a snapshot	SNAPSHOT snapshot /MAP:drive
Unmap a snapshot	SNAPSHOT snapshot /UNMAP
Delete a snapshot	SNAPSHOT snapshot /DELETE [/UNMAP]
Show snapshots	SNAPSHOT [snapshot]

Show available storage units	UNITS
------------------------------	-------

Create a virtual disk	VIRTUALDISK virtualdisk /POOL:pool /CAP:mb
Map a virtual disk	VIRTUALDISK virtualdisk /MAP:drive
Format a virtual disk	VIRTUALDISK virtualdisk /FORMAT
Unmap a virtual disk	VIRTUALDISK virtualdisk /UNMAP
Delete a virtual disk	VIRTUALDISK virtualdisk /DELETE [/UNMAP]
Show virtual disks	VIRTUALDISK [virtualdisk]
Grow a virtual disk	VIRTUALDISK virtualdisk /GROW:mb

NDMgr Commands

Show available drive letters	DRIVES [/NODE:nodename]
Manage remote computer	MANAGE computername
Manage local computer	MANAGE /LOCAL
Show managed computer	MANAGE

Add registered client	REGISTER netdiskname clientname
Remove registered client	REGISTER netdiskname clientname /DELETE
Show registered clients	REGISTER netdiskname

Serve a disk	SERVE netdiskname drive
Stop serving a disk	SERVE netdiskname /DELETE
Show served disks	SERVE [netdiskname]

Connect to a disk	USE drive \\servername\netdiskname USE * \\servername\netdiskname
Disconnect from a disk	USE \\servername\netdiskname /DELETE USE drive /DELETE
Show connected disks	USE [\\servername\netdiskname] USE drive

NOTE: You can only use MANAGE commands at the SnapMgr or NDMgr prompt. You cannot use them at the Windows NT command prompt.

If you are working from the Windows NT prompt, the commands will manage the local computer, unless you include the name of a remote computer in the command line. For example:

```
C:\>NDMGR Accounts DRIVES
```

```
C:\>SNAPMGR Engineering UNITS
```